

Below are the steps you can use with a USB flash memory stick to transfer a text/ASCII file from a SurvCE to a desktop or laptop computer:

- 1. Create a folder in your USB Flash Memory drive such as "USB Data" while its connected to your computer
- 2. Insert the USB thumb drive into the data collector
- 3. Open the Job that you are working on in SurvCE
- 4. Under the File menu, tap Import/Export

😂 JOB:CONTROLTEST 🗧  🚺				7	
<u>F</u> ile	Equip	<u>S</u> ur	vey	<u>C</u> OGO	<u>R</u> oad
<u>1</u> Job		2	6Data Transfer 😽		
<u>2</u> Job Set	tings	<b>s 😂 Z</b> Import/Export		rt 📴	
<u>3</u> Points		ΙΞ	<u>8</u> De	lete Job	9
4Raw Da	ita	5	<u>9</u> Wr	ite Note	🥒
<u>5</u> Feature	Code List		<u>O</u> Exi	t	- 1

5. Tap Export ASCII.

ờ Impor	rt/Export	×
	Import Ascii File	
	<u>E</u> xport Ascii File	

This document contains confidential and proprietary information that remains the property of Carlson Software Inc.



6. Leave the File Type set to User Defined. Confirm your coordinate order and point range. Then, tap the green check mark.

😂 Export	Ascii		🔽 🗙
File Type: Coordinate PT_ID,Nort	User Defi Order: h,East,Elev,Desc	ined T	<b>▼</b> Confiq
Delimiter © Comn	na () Space ()	Tab () Ot	her
Range: Precision:	1-24 0.0000 ▼	Export	Point Notes Point Info Attributes
Form	nat Geodetic	]	

7. You will be prompted to name your text/ASCII file, as well as where to save it. Most likely, your data collector is set to save your text file in the same location as your CRD file. The image below shows where the program is currently set to Save.

Ascii File to Write			X
Type: TXT Files		* 🖽	
違 \Program Files\SurvCE\D	ata\ 🧲		
Backup			
Name: controltest.txt			

This document contains confidential and proprietary information that remains the property of Carlson Software Inc.



8. Tap on the icon of the folder with the Up arrow, until the "data path" shows only a backslash.



9. Double-tap on the folder called Hard Disk. This is your USB thumb drive.

ờ Ascii File to Write 👘	(B) (b) 🔽 🗙
Type: TXT Files	- 🌶 🏓 🖽 🔲
<u>ت ۱</u>	
🚞 Application Data	🚞 Program Files
🚞 Carlson_DevInfo	🚞 Storage
🚞 ConnMgr	🛃 dumpmem.txt
Documents and Settings	
🔁 Hard Disk	
MUSIC	
🚞 My Documents	
◀ Ⅲ	•
Name: controltest.txt	



10. Next, double-tap on the folder which we had created in step one, called USB Data.

😂 Ascii File to Write	
Type: TXT Files	- 🎓 📂 📖
🗀 \Hard Disk\	
🚞 Carlson Art	
MAGES	
USB DATA	
SERIAL.txt	
Name: <mark>controltest.txt</mark>	

11. Your "data path" should now be set to \Hard Disk\USB Data\. Tap the green check mark to export your text/ASCII file to this location on your thumb drive.

裬 Ascii File to Write 👘			$\checkmark$	X
Type: TXT Files	- 🧯	<b>)</b> 📂		
🚞 \Hard Disk\USB DATA\	<			
1503-1506.txt				
Ball Park 7016-7022.000				
Name: controltest.txt				

12. You may now unplug the USB thumb drive and plug it into your PC to obtain your data.