

Before getting started, have all users close the Carlson programs on their workstations.

- 1. Download, and save, the updated license management software (<u>Sentinel Server 9.5.0221</u>), and <u>its Tools</u>, to your Server Computer.
- 2. Click on the Windows menu icon on your taskbar. Then, type **Administrative** to search for Administrative Tools.

Best match						
Windows Administrative Tools						
Settings						
🔎 admini						
FogBugz (Case 286 📙 License Manageme						

- 3. Double-click on Services.
- 4. Stop the Sentinel RMS service.

Services (Local)					
Sentinel RMS License Manager	Name	Description	Status	Startup Type	Log ^
	🌼 Sensor Monitoring Service	Monitors va		Manual (Trig	Loci
Stop the service	🏟 Sensor Service	A service fo		Manual (Trig	Loci
Restart the service	🌄 Sentinel RMS License Mana	Sentinel RM	Running	Automatic	Loci
	🔍 Server	Supports fil	Running	Automatic (T	Loci
	🎑 Shared PC Account Manager	Manages pr		Disabled	Loci
Description: Sentinel RMS License Manager	🎑 Shell Hardware Detection	Provides no	Running	Automatic	Loci
	🏟 Smart Card	Manages ac		Manual (Trig	Loci
1	285			· · ·	

- 5. Left-click on the Windows menu icon on your taskbar. Select Apps and Features.
- 6. Uninstall the existing Sentinel RMS Service.
- 7. Run the **SentinelRMS X.exe**.
- 8. Follow the installation instructions. Be sure to leave the installation settings at their default. This will include the option to "Unblock the system firewall for the Sentinel RMS License Manager".
- 9. Return to the Administrative Tools/Services and restart the Sentinel RMS service.

This document contains confidential and proprietary information that remains the property of Carlson Software Inc.



- 10. Extract the Carlson LMTools 9_5_0221. These tools will replace your existing Carlson LMTools and have not changed with the newer RMS server version.
- 11. Within this new folder, you will find the WLMAdmin.exe. You may launch this to see that your network licenses have been picked up by the new Sentinel Service.

S WImAdmin		_		×	
<u>F</u> ile <u>E</u> dit <u>V</u> iew <u>T</u> ools <u>H</u> elp					
Defined Servers Subnet Servers B- APRIL_2015 B- DESKTOP-4VLV7J6	Server information Name: HAMMER-PC IP address: HAMMER-PC	9.5.0.0221			^
	Feature information Name: Statistics	Version:			
	Inu	ise: Total	:	Queued:	

This document contains confidential and proprietary information that remains the property of Carlson Software Inc.