

Leica SurvCE Training

Installing USB driver for RX1250



Table of Contents

1.0	Introduction	2
2.0	Before You Begin	2
3.0	Installation of Software	2

1.0 Introduction

Objectives

In this exercise you will install the USB driver that is required for direct communication between the RX1250 and a PC.

2.0 Before You Begin

Getting Started

All you need for this exercise is the Leica SurvCE Installation CD, the RX1250, and a GEV161.

3.0 Installation of Software

Objectives

Install the USB driver for the RX1250



Insert the **Leica SurvCE Installation CD** into the CD-Rom drive of your computer.

From the main screen that is displayed when the Installation CD is inserted in your computer it is not necessary to select anything.


Installing USB OmniDrive



Connect the RX1250 to your PC using the GEV161 cable.

Select **Install the software Automatically**


Click **Next**



Windows will search for the appropriate driver on the Installation CD.



Click **Continue Anyway**



Click **Finish**

The driver has been successfully installed.