

Leica SurvCE Training



Table of Contents

1.0	Introduction	2
2.0	Before You Begin	2
3.0	Installation of Software	2

1.0 Introduction

Objectives

In this exercise you will install Microsoft ActiveSync.

2.0 Before You Begin

Getting Started

All you need for this exercise is the Leica SurvCE Installation CD, a GEV161 cable, and the RX1250.

3.0 Installation of Software

Objectives


Install Microsoft ActiveSync and establish communication between the RX1250 and a PC.

Installing Microsoft ActiveSync




Insert the **Leica SurvCE Installation CD** into the CD-Rom drive of your computer.

From the main screen that is displayed when the Installation CD is inserted in your computer select **Software**.



Select **Microsoft ActiveSync**

You will be instructed to connect the cable at the appropriate time.



Click **Next**

Accepting the EULA



Place a bullet in **I accept the terms of the license agreement.**

Click **Next**

Entering your Information

Enter the following:


- **Your Name**
- **Your Company Name**

Click **Next**

Click **Next**


Click **Next**

Page 4



Click **Finish**

**ActiveSync
automatically
connects**




Connect the RX1250 to the PC
via the GEV161 cable

ActiveSync should automatically
connect within a few seconds of
plugging in the cable.



Select **NO**

Click **Next**



This window can be minimized or closed without interrupting the connection.

The connection will be severed when you disconnect the cable from either device.